

# **ABBYY FlexiCapture 12 Release 2 Update 8 Release Notes**

---

# Table of Contents

---

**INTRODUCTION ..... 3**

**About this document..... 3**

**About the product..... 3**

**About the update ..... 3**

**TECHNICAL INFORMATION..... 3**

**NEW FUNCTIONALITY ..... 3**

**1. Full self-service scenario on Web Verification Station: new filter for manual data export on local machine..... 3**

**BUG FIXES ..... 4**

# Introduction

## About this document

This document describes the changes made in ABBYY FlexiCapture 12 Release 2 Update 8.

## About the product

ABBYY FlexiCapture 12 is a new version of the FlexiCapture product, whose main goal is to provide a stable and scalable Data Capture platform that can serve as a basis for creating regional and vertical solutions.

## About the update

The update includes new features and bug fixes. It can be installed on its own or on top of ABBYY FlexiCapture 12 Release 1 or Release 2 with any updates installed.

# Technical Information

Release	Part #	Build #	Installer build #	OCRT build #	Release date
<b>Release 2 Update 8</b>	<b>1299/31</b>	<b>12.0.2.3068</b>	<b>41234</b>	<b>16.1.528.15</b>	<b>2019.04.02</b>
Release 2 Update 7	1299/30	12.0.2.3042	36892	16.1.528.9	2019.03.07
Release 2 Update 6	1299/29	12.0.2.1420	29512	16.1.251.84	2018.12.28
Release 2 Update 5	1299/28	12.0.2.1398	27056	16.1.251.75	2018.12.05
Release 2 Update 4	1299/27	12.0.2.1387	25159	16.1.251.75	2018.11.22
Release 2 Update 3	1299/26	12.0.2.1370	22855	16.1.251.68	2018.10.30
Release 2 Update 2	1299/25	12.0.2.1363	21603	16.1.251.66	2018.10.19
Release 2 Update 1	1299/24	12.0.2.1356	20560	16.1.251.66	2018.10.05
Release 2	1299/22	12.0.2.1194	16090	16.1.251.47	2018.08.03

# New functionality

## 1. Full self-service scenario on Web Verification Station: new filter for manual data export on local machine

For the manual data export scenario, a new filter has been added to the filter drop-down list in batch view. This filter shows batches that have never been downloaded.

The screenshot shows the 'FlexiCapture Verification' web interface. The 'Batches' tab is selected. A dropdown menu is open, showing the filter 'Processed but non-downloaded batches'. The main table displays the following data:

Batch Type	Stage Name	Creation time	Documents	Pages	Expiration date	ID	Last download time
Default	Processed	3/29/2019 11:51 AM	1	5		20	
Default	Processed	3/27/2019 3:53 PM	1	5		8	

This filter is disabled by default. To enable it, use the CanDownloadBatchResult key in the web.config file (the default location of the web.config file is inetpub\wwwroot\FlexiCapture12\Verification on each web station).

## Bug Fixes

Issue description
<p>FlexiCapture Standalone. Automatic import from "hot folders" stops if any error occurs and the administrator has to resume it manually. This leads to unnecessary manual effort and the administrator's intervention even in the event of occasional harmless network errors. Now a Windows registry key is available that prevents automatic import from stopping even when errors occur.</p> <p>To prevent import from stopping, set the Windows registry key</p> <p>"HKEY_CURRENT_USER\Software\ABBYY\FlexiCapture\12.0\Shell\Import\ContinueAutoImportDespite Errors" to "true".</p> <p>By default, this key is set to "false" (i.e. import will stop on errors).</p>
<p>When a scripting processing stage failed due to an unhandled exception in the user code, there was no message in the processing notes for the document. Now, processing notes contain an error message.</p>
<p>In some rare cases, the Project Setup Station crashed when trying to upload onto the server a project updated to the latest version. Now uploads successfully without crashing.</p>
<p>The priority was not correctly defined (one level lower than it should be) when sending a new batch from the Web or Desktop Scanning Station. Now it defines correctly.</p>
<p>Licence Manager: On a system with the EN user interface, the "Expiration Date" value was in RU (Russian).</p>
<p>Fixed an error caused by inputting Japanese text using Microsoft's Japanese IME on the Web Verification Station. After a spelling variant selected from the list of suggestions was confirmed, the cursor position was reset to the beginning of the field, and the spaces disappeared.</p>
<p>An installed Remote Scanning Station could not be started because some of the files were missing in the Scanning Station installation package.</p>
<p>The "Dates" element in FlexiLayout Studio did not work for dates in Ukrainian.</p>